

## Smuxi - Bug # 345: password with only digits fail to work with remote engines

<b>Status:</b>	Closed	<b>Priority:</b>	Normal
<b>Author:</b>	Mikail Altunbas	<b>Category:</b>	Engine
<b>Created:</b>	02/10/2010	<b>Assigned to:</b>	Mirco Bauer
<b>Updated:</b>	06/06/2010	<b>Due date:</b>	
<b>Complexity:</b>	Low		
<b>Subject:</b>	password with only digits fail to work with remote engines		
<b>Description:</b>	<p>adding a remote engine to the frontend with a number only password works, but when connecting it fails with:</p> <pre>&lt;pre&gt; An error occurred while connecting to the engine!  Engine URL: Error: Cannot cast from source type to destination type. &lt;/pre&gt;  when trying to edit, it fails with: &lt;pre&gt; Exception Type: System.InvalidCastException  Exception Message: Cannot cast from source type to destination type.  Exception StackTrace:   at Smuxi.Frontend.Gnome.EngineAssistant.InitCredentialsPage () [0x00000]   at Smuxi.Frontend.Gnome.EngineAssistant.InitPages () [0x00000]   at Smuxi.Frontend.Gnome.EngineAssistant..ctor (Gtk.Window parent, Smuxi.Engine.FrontendConfig config, System.String engineName) [0x00000]   at Smuxi.Frontend.Gnome.EngineManagerDialog._OnEditButtonPressed () [0x00000]     at Smuxi.Frontend.Gnome.EngineManagerDialog._OnResponse (System.Object sender, Gtk.ResponseArgs e) [0x00000] &lt;/pre&gt;</pre>		

### Associated revisions

**06/06/2010 06:21 PM - Mirco Bauer**

Fixed InvalidCastException when using engine passwords with only digits. (closes: #345)

### History

**06/06/2010 06:23 PM - Mirco Bauer**

- Target version set to 0.7.2

- Complexity set to Low

**06/06/2010 06:23 PM - Mirco Bauer**

- Status changed from New to Closed

- % Done changed from 0 to 100

Applied in changeset commit:"7314e59a128b062e249a3a6bbdb7cb906fd0c023".